



Rota Yokogawa - **Flowcenter of Excellence**

Installation Procedure for the “Flow Configurator 3.5”:

1. Make sure you have the latest service pack and critical updates for the version of Windows® that you are running. To find recent security updates, visit [Windows® Update](#) .
If you have already installed the Microsoft® .NET Framework 1.1-package
You can skip items 2 to 4 and continue the installation from item 5.
2. Download the [.NET Framework Version 1.1 Redistributable Package](#) from the Microsoft® Download site and install the package following the instructions given by Microsoft. (Alternatively you can start CD:\Microsoft\1.1\dotnetfx.exe from the CD) Choose the appropriate language of the package corresponding to the language of your Windows® version.
3. Download and install the [Microsoft® .NET Framework 1.1 Service Pack 1](#) from the Microsoft® Download site (or use the file
“CD:\Microsoft\1.1\sp1\NDP1.1sp1-KB867460-X86.exe” from the CD) and install the Service Pack following the instructions given by Microsoft. Choose the appropriate language of the package corresponding to the language of your Windows® version.
4. Download and install the [ASP.NET Security Update for Microsoft® .NET Framework 1.1 Service Pack 1](#) from the Microsoft® Download site (or use
“CD:\Microsoft\1.1\Update_sp1\NDP1.1sp1-KB886903-X86.exe” from the CD) and install the Security Update following the instructions given by Microsoft. Choose the appropriate language of the package corresponding to the language of your Windows® version.
5. If necessary download and install the [Microsoft® .NET Framework Version 1.1 Language Pack](#) from the Microsoft® Download site and install the Language Pack following the instructions given by Microsoft. Choose the appropriate language of the package corresponding to the language of your Windows® version.
6. Only for Windows® 2000 you have to install „ MDAC_TYP8.EXE“ from the CD (“CD:\Microsoft\MDAC_TYP8.EXE”) additionally.
7. You can either download the Flow Configurator Version 3.5 with the directly from the FLP or order a CD from fcp.info@de.yokogawa.com. After you have downloaded the Setup.zip-file, please extract it. Start Setup.exe from the install CD or from the extraction path and follow the instructions given.
8. Every user of the installed sizing program must have **modify permissions** for the chosen install path of step 7.



Rota Yokogawa - **Flowcenter of Excellence**

9. You can start the program by double-clicking the icon “ Yokogawa Sizing” on the desktop.
10. In order to remove the FlowConfigurator simply completely delete the install path from step 7 and delete the link from the desktop.
11. For printing to pdf-files an appropriate Tool is required. A freeware pdf-converter is available at <http://shbox.de/fpxp.htm>